



Clarity II-O

Mobile App Guide

Android App: [View on Google Play](#)
iOS App: [View on App Store](#)

Using the Rize Clarity II-O mobile app

Your adjustable bed can be controlled using your iOS or Android smart device through the Rize Clarity II-O mobile app.

Before connecting your bed to the mobile app, do the following:

- Make sure your adjustable bed is plugged into a working electrical outlet and the control box is on.
- Download and install the Rize Clarity II-O mobile app from the App Store® or the Google Play Store™.
- For iOS users, turn on your device's Bluetooth®. For Android users, turn on your device's Bluetooth® and Location settings.



Connecting to your adjustable bed

1. If you are connecting your bed to the mobile app for the first time, enable the mobile device pairing mode on your bed's control box.

Do one of the following:

- Unplug the power cord from the outlet and then plug it back in. The LED light on the control box turns blue. After 20 seconds, the LED light turns green and the control box enters mobile device pairing mode.
- On the control box, press the **PAIR** button twice. The LED light turns blue. After 20 seconds, the LED light turns green and the control box enters the mobile device pairing mode.

NOTE: The control box stays in mobile device pairing mode for 60 seconds and the name of your bed is now visible on the app. Proceed to step 2 to connect the mobile app to your adjustable bed.



Option 1. Unplug the power cord, and then plug it back in.



Option 2. Press the PAIR button on the control box twice.

Connecting to your adjustable bed

- From your mobile device, launch the app, and then tap the gear icon to go to the **Settings** screen.
- From the Devices list, select the name of your adjustable bed. The name of your adjustable bed is on the sticker on the front cover of the Owner's Manual and on the bed's control box.


NOTES:

- If your bed is not on the Devices list, make sure your bed is in mobile device pairing mode. See step 1 for options to enable the mobile device pairing mode on your bed's control box.
- You can only connect one smart device to one adjustable bed at a time.
- The bed is automatically disconnected from the app when you close the app (not running in the background) or move out of range of the connection. Pair the bed to the app again next time you use the app.



Sample sticker with the name of your adjustable bed.

Controlling the head or foot sections of your bed



Tap and hold the (+) or (-) buttons for the head or foot section of your adjustable bed to raise or lower them.

To control the head and foot sections using voice commands, tap the microphone button in the center of the screen.

NOTE: The Voice Commands List can be found on page 10.

To switch between the screens of your app, swipe left or right.

Controlling the bed presets



Tap the preset button you want to activate. The preset buttons are ANTI SNORE, LEISURE, ZG (Zero Gravity), INCLINE, and FLAT.

To customize the presets, adjust your bed to the desired position then tap and hold the preset button for 3 seconds.

NOTES:


- This is only available for Leisure, Incline, and ZG buttons.
- To restore the preset positions back to factory settings, reset the system using the remote control. For more information, see the “Resetting the system” topic on your Owner’s Manual.

To activate the presets using voice commands, tap the microphone button in the center of the screen.

NOTE: The Voice Commands List can be found on page 10.

To switch between the screens of your app, swipe left or right.

Controlling the message feature



Tap the different message buttons to turn on your bed's massage feature. Tap the STOP button to turn off any active massage.

To increase or decrease the massage intensity, tap and hold the (+) or (-) button.

To change the different massage feels, tap the different wave buttons.

To activate the massage feature using voice commands, tap the microphone button in the center of the screen.

NOTE: The Voice Commands List can be found on page 10.

To switch between the screens of your app, swipe left or right.

Controlling the under-bed lights



Tap the light button to turn your under-bed lights on. Tap it again to turn the lights off.

To activate the under-bed lights using voice commands, tap the microphone button in the center of the screen.

NOTE: The Voice Commands List can be found on page 10.

To switch between the screens of your app, swipe left or right.

Controlling two adjustable beds in tandem

Before operating beds in tandem using the mobile app, do the following:

- Make sure both beds are plugged into working electrical outlets.
 - Make sure both beds are in a flat position to align them properly.
1. Connect the sync cable to the SYNC port on the control box of both adjustable beds.
 2. Connect the mobile app to either one of the beds.

As long as both adjustable beds are connected with the sync cable, you can operate both beds in tandem using only one mobile device.



Connect the sync cable to the control box on both beds to operate them in tandem mode using the mobile app.



Voice Commands List

To activate the functions of your adjustable bed using voice commands, tap the microphone button in the center of your screen.

A message prompts you to say the voice command. If the command is correct, the message disappears and the bed adjusts accordingly. If the command is incorrect, a pop-up appears prompting you to speak the correct command. To dismiss the prompt after an incorrect command, tap anywhere outside the message. Tap the microphone button again to give the correct voice command.

NOTE: Make sure to speak the exact phrases in the list below for the bed to function properly according to the command.

Head Up - Lifts head section.

Head Down - Lowers head section.

Foot Up - Lifts foot section.

Foot Down - Lowers foot section.

Stop - Stops all lift activities.

Leisure - Activates the Leisure position.

Zero - Activates the Zero Gravity position.

Snore - Activates the Anti-Snore position.

Incline - Activates the Incline position.

Flat - Activates Flat position.

Massage On - Starts massage wave 1.

Wave One - Starts massage wave 1.

Wave Two - Starts massage wave 2.

Wave Three - Starts massage wave 3.

Massage Off - Turns massage motors off.

Light On / Lights On - Activates the under-bed light.

Light Off / Lights Off - Turns the under-bed light off.



FOR ASSISTANCE, PLEASE CALL OUR
CUSTOMER SERVICE TOLL FREE NUMBER

1-843-800-8372

POWERED BY CUSTOMATIC® TECHNOLOGIES™

All product names, brands, and trademarks are the property of their respective owners.